Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page 1 of 10			
Product	Name CBASIC Compiler for ND-500/5000	Reg. no. Category 211035B STPR			
Reason	_	or Correction ferent Environment			
Documen- tation	Title CBASIC Referenzhandbuch CBASIC Bibliotheksaufrufe Referenz CBASIC Befehlsübersicht	Reg. no. 860243.2 DE zkarte 899125.1 DE 899126.1 DE			
Purpose	CAT-Compiler and Library System for language CBASIC for ND-500/5000	or programming			
Prerequi- sites	Computer Type Floating format Op. system Version ND-500/5000 All All SINTRAN III >= J				
	Reg. no. Product name 210319F Linkage-Loader for ND-	500/5000			
-	Minimum mass storage resources for User User space DOMAIN-USER 381 pages on SYSTEM 520 pages on CAT-CBASIC 610 pages on	Number of files 13 files 6 files			
	Minimum permanent mass storage results of the User space User space DOMAIN-USER 381 pages on SYSTEM 520 pages on CAT-CBASIC 610 pages on	Number of files 13 files 6 files			
Product consists of		Reg. no. for Source 250169B06			
FILES INCLU	JDED ON THE SYSTEM DISKETTES:				
File Name	File Name Type Containing				
DESCRIPTION-FILE DESC SCRATCH-SEG-01 LINK SCRATCH-SEG-01 PSEG SCRATCH-SEG-01 DSEG CAT-CAT5-B06 LINK CAT Code Generator 500 CAT-CAT5-B06 PSEG CAT Code Generator 500					

			<u> </u>		
Date 89.06	.16		k Data A.S M DESCRIPTION	Page	2 of 10
Product	Name CBASIC Co	mpiler for	r ND-500/5000	Reg. no. 211035B	Category STPR
CAT-CAT5-II CAT-CAT1-II CAT-CAT1-II CAT-CAT1-II CAT-LIB-BO CAT-ZBANK- CAT-FREE-II CAT-MAXDAT ENTER INST-CBA-II CBA-IIB-BO CBA-IIB-BO CBA-LIB-BO CBA-ISAM-II CBA-MONITO CBA-SIBAS- CBA-RENUMI CBA-DEBUG- CBA-SPR-LII CBASIC-EXXIINST-CBA-II	806 806 806 -806 -806 806 FA-B06 500-1 0-B06 0-B06 0-B06 -806 -806 0R-B06 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806 -806	DSEG LINK PSEG DSEG NRF BRF BRF PROG MODE LING DSEG NRF BRF SYMB SYMB SYMB SYMB SYMB SYMB SYMB SYMB		CAT Code General CAT Code General CAT Code General CAT Code General CAT-Library CASIC-Compilion CASIC-Compilion CASIC-Library CASIC-Library CASIC-Include CASIC-Include CASIC-Include CASIC-Include CASIC-Library CASIC-Example Installation	Program mode ler for 500 ler for 500 ler for 500 ry ry de-file de-file de-file de-file rogram ry ry ry ry

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	3 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

# 1 ND-SOFTWARE LIBRARY DISKETTE

Containing : CBASIC Compiler for ND-500/5000

Directory Name: 211035B06-XX-01D

User Name : FLOPPY-USER

File	access:
1116	access.

Nr	File name	Туре	T	Public	Friend	Own	Pages	Bytes
0	DESCRIPTION-FILE	DESC	I	R	R	RWACI	8	22528
1	SCRATCH-SEG-01	LINK	I	R	R	RWACI	0	0
2	SCRATCH-SEG-01	<b>PSEG</b>	I	R	R	RWACI	1	5
3	SCRATCH-SEG-01	DSEG	I	R	R	RWACI	) 1	1029
4	CAT-CAT5-B06	LINK	I	R	R	RWACI	0 0	0
5	CAT-CAT5-B06	PSEG	I	R	R	RWACI	64	128176
6	CAT-CAT5-B06	DSEG	I	R	R	RWACI	65	145789
7	CAT-CAT1-B06	LINK	I	R	R	RWACI	0 0	0
8	CAT-CAT1-B06	PSEG	I	R	R	RWACI	56	110574
9	CAT-CAT1-B06	DSEG	I	R	R	RWACI	53	118845
10	CAT-LIB-B06	NRF	I	R	R	R	108	220885
11	CAT-MAXDATA-B06	BRF	I	R	R	R	1	32
12	CAT-2BANK-B06	BRF	I	R	R	R	117	239056
13	CAT-FREE-BO6	BRF	I	R	R	R	1	282
14	ENTER	PROG	I	R	R	R	5	4608
15	INST-CBA-500-1	MODE	I	R	R	R	3	3344

<sup>16</sup> files 483 pages used out of 610 pages.

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	4 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

# 2 ND-SOFTWARE LIBRARY DISKETTE

Containing : CBASIC-500 Compiler for ND-500/5000

Directory Name: 211035B06-XX-02D

User Name : FLOPPY-USER

	-	
P.3	10	access:
L T	15	aucss.

Nr	File name	Туре	T	Public	Friend	Own :	Pages	Bytes
0	DESCRIPTION-FILE	DESC	I	R	R	RWACD	8	22528
1	SCRATCH-SEG-01	DSEG	I	R	R	RWACD	1	1029
2	SCRATCH-SEG-01	LINK	I	R	R	RWACD	0	0
3	SCRATCH-SEG-01	PSEG	I	R	R	RWACD	1	5
4	CBASIC-500-B06	LINK	I	R	R	RWACD	7	13697
5	CBASIC-500-B06	PSEG	I	R	R	RWACD	86	174134
6	CBASIC-500-B06	DSEG	I	R	R	RWACD	37	88685
7	CBA-LIB-BO6	NRF	I	R	R	R	137	278977
8	CBA-2BANK-B06	BRF	I	R	R	R	129	263990
9	CBA-FOCUS-BO6	SYMB	I	R	R	R	3	4264
10	CBA-ISAM-BO6	SYMB	I	R	R	R	2	3107
11	CBA-MONITOR-B06	SYMB	I	R	R	R	7	12897
12	CBA-SIBAS-BO6	SYMB	I	R	R	R	3	4099
13	CBA-RENUMBER-B06	PROG	I	R	R	R	53	212992
14	CBA-DEBUB-B06	NRF	I	R	R	R	11	21631
15	CBA-DEBUG-B06	BRF	I	R	R	R	9	17483
16	CBA-SPR-LIB-B06	BRF	I	R	R	R	22	<b>4</b> 3806
17	CBA-SPR-LIB-BO6	NRF	I	R	R	R	21	<b>4</b> 1775
18	ENTER	PROG	I	R	R	R	5	<b>4</b> 608
19	CBASIC-EXAMPLES	CBAS	I	R	R	R	1	105
20	INST-CBA-500-2	MODE	I	R	R	R	3	5655

<sup>21</sup> files 546 pages used out of 610 pages.

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	5 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

#### 3 INSTALLATION PROCEDURE

Before installing:

- Check whether there is a LINKAGE-LOADER or ND-LINKER on your system.
- Check with <u>USER-STATISTICS DOMAIN-USER</u>, whether the user <u>DOMAIN-USER exists</u>.

If user DOMAIN-USER does not exist:

- Log in as user SYSTEM!
- Enter:

@CREATE-USER DOMAIN-USERJ @GIVE-USER-SPACE DOMAIN-USER 381J

If there is a user DOMAIN-USER, but less than 381 unused pages of disk space on user DOMAIN-USER: Let n be the difference between 381 and the number of unused pages on user area DOMAIN-USER,

- Log in as user SYSTEM
- @GIVE-USER-SPACE DOMAIN-USER n↓
- Check with @USER-STATISTICS, SYSTEM, , , whether there
  are at least 520 unused pages of disk space on user SYSTEM.

  If there are less pages of disk space:
  let n be the difference between 520 and the number of unused
  pages on user SYSTEM,
  - Log in as user SYSTEM
  - @GIVE-USER-SPACE SYSTEM nJ
- Check with @USER-STATISTICS CAT-CBASIC,, whether the user CAT-CBASIC exists.

If user CAT-CBASIC does not exist:

- Log in as user SYSTEM!

@CREATE-USER CAT-CBASIC!

@GIVE-USER-SPACE CAT-CBASIC 610;

Log in as user CAT-CBASIC;

@SET-DEF-FILE-ACC R,R,RWACD;

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	6 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

If there is a user CAT-CBASIC but less than 610 pages of disk space on user CAT-CBASIC: Let n be the difference between 610 and the number of pages on user CAT-CBASIC;

- Log in as user SYSTEMJ
- @GIVE-USER-SPACE CAT-CBASIC nJ

### Now you can install CAT-CBASIC:

- Log in as user SYSTEMJ
- Insert Floppy 211035B06-XX-01D into the disk drive.
- @ENT-DIR,,F-D-1,<UNIT>, MODE (211035B06-XX-01D:FLOPPY-USER)INST-CBA-500-1:MODE,,,.
- Release the floppy-disk with @REL-DIR 211035B06-XX-01DJ
- Insert Floppy 211035B06-XX-02D into the disk drive.
- @ENT-DIR,,F-D-1,<UNIT>, MODE (211035B06-XX-02D:FLOPPY-USER)INST-CBA-500-2:MODE,,,
- Check whether the CBASIC-program CBASIC-EXAMPLES had run!
- Release the floppy with @REL-DIR 211035B06-XX-02DJ
- Insert the following commands into the file HENT-MODE: MODE

@nd DEFINE-STANARD-DOMAIN CAT-CAT5-B (DOMAIN-USER)CAT-CAT5-BJ DEFINE-STANARD-DOMAIN CAT-CAT1-B (DOMAIN-USER)CAT-CAT1-BJ DEFINE-STANARD-DOMAIN CBASIC-500-B (DOMAIN-USER)CBASIC-500-BJ EXITJ

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	7 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

# 4 MODIFICATIONS AND CHANGES SINCE VERSION BO2

- CBA-100-B06 / CBA-500-B06
   Corrections:
  - The statement "PRINT NUM(A\$(0,2)):NUM(A\$(2,2));B\$" is no longer valid, as the generated code could have been incorrect.

    Alternative: "X=NUM(A\$(0,2)),Y=NUM(A\$(2,2))@PRINT X:Y;B\$"
  - SEGNAME "NAME": control characters were passed along with the name.
- CAT-MAXDATA-B06:BRF
  The file is new. It is required for ND-100 and RT-Program.
- CAT-CAT5-B06 / CAT-CAT1-B06
   Extensions have been implemented for the C-Compiler and the PASCAL-Compiler.
- CBA-SPR-2B-B06 / CBA-SPR-LIB-B06
  The library is new. It has been generated for SPRINT (spooling). See enclosure.
- CBA-2BANK-BO6 / CBA-LIB-BO6 Corrections:
  - UCASE(A\$): The internal limit has been extended from 128 to 512 Bytes.
  - DLEN: If the number of a record was outside the limits of a record file error 100 was reported.
  - Tape-calls: Incorrect error numbers were reported. (Tape empty, error in block length, file mark read).
  - DISAM-calls: If a record was locked, error 1 was reported after approximately five minutes.
  - Remote-DISAM: The functions REMOTE-KILL, REMOTE-CLOSE, REMOTE-KINV, REMOTE-COKEY and REMOTE-DALT have been corrected.
  - IF a user name was exactly 16 characters long, the file name was incorrect.
  - RUN: the DOMAIN-format of the new linker is implemented.

#### New:

- The call MOVE TO (see enclosure).

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	8 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

### 5 ANLEITUNG ZUR INSTALLATION

Vor Beginn der Installation sind folgende Punkte zu beachten.

 Prüfen, ob ein lauffähiger LINKAGE-LOADER oder ND-LINKER auf dem System vorhanden ist:
 Nach L-L muß sich der LINKAGE-LOADER melden.
 Mit EX den LINKAGE-LOADER verlassen.

• Mit <u>USER-STATISTICS DOMAIN-USER</u> prüfen, ob ein Benutzerbereich <u>DOMAIN-USER</u> vorhanden ist.

Falls kein Benutzerbereich DOMAIN-USER vorhanden ist:

- Einloggen in den Benutzerbereich SYSTEM.
- Folgende Kommandos eingeben: CREATE-USER DOMAIN-USER und GIVE-USER-SPACE DOMAIN-USER 381

Falls der Benutzerbereich DOMAIN-USER vorhanden ist, aber weniger als 346 freie Pages zur Verfügung stehen, muß Platz geschaffen werden:

n sei die Differenz zwischen 381 und der Anzahl freier Pages auf dem Benutzerbereich DOMAIN-USER;

- Einloggen als User SYSTEM.
- GIVE-USER-SPACE DOMAIN-USER n
- Prüfen, ob auf dem Benutzerbereich SYSTEM 520 freie Pages vorhanden sind: USER-STATISTICS, USER-SYSTEM, , eingeben.

Ist zu wenig Platz vorhanden, muß Platz geschaffen werden: n sei die Differenz zwischen 520 und der Anzahl freier Pages auf dem Benutzerbereich SYSTEM; GIVE-USER-SPACE SYSTEM n

• Mit <u>USER-STATISTICS CAT-CBASIC</u>, prüfen, ob ein Benutzerbereich CAT-CBASIC vorhanden ist.

Falls kein Benutzerbereich CAT-CBASIC vorhanden ist:

- Einloggen als User SYSTEM.
- Den Benutzerbereich anlegen mit:
  CREATE-USER CAT-CBASIC
  GIVE-USER-SPACE CAT-CBASIC 610
  Einloggen als User CAT-CBASIC und
  SET-DEF-FILE-ACC R,R,RWACD eingeben.

ND-895276, XX

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page	9 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

Falls der Benutzerbereich CAT-CBASIC vorhanden ist, aber weniger als 610 Pages zur Verfügung stehen, muß Platz geschaffen werden:

n sei die Differenz zwischen 610 und der Anzahl der vorhandenen Pages auf dem Benutzerbereich CAT-CBASIC;

- Einloggen als User SYSTEM.
- GIVE-USER-SPACE CAT-CBASIC n

Nun kann installiert werden.

- Floppy 211035B06-XX-01D ins Laufwerk einlegen.
- Die Floppy anmelden mit ENT-DIR, ,F-D-1, <UNIT>,
- Das Kommando MODE (211035B06-XX-02D:FLOPPY-USER)INST-CBA-500-1:MODE,,, ausführen.
- Die Floppy abmelden mit REL-DIR 211035B06-XX-01D
- Die Floppy 211035B06-XX-02D ins Laufwerk einlegen.
- Die Floppy anmelden mit ENT-DIR, ,F-D-1, <UNIT>,
- Das Kommando MODE (211035B06-XX-02D:FLOPPY-USER)INST-CBA-500-2:MODE,,, ausführen und prüfen ob das CBASIC-Programm CBASIC-EXAMPLES gelaufen ist.
- Die Floppy abmelden mit REL-DIR 211035B06-XX-02D
- In die Datei HENT-MODE: MODE die folgenden Kommandos eintragen:

@nd
DEFINE-STANARD-DOMAIN CAT-CAT5-B (DOMAIN-USER)CAT-CAT5-B
DEFINE-STANARD-DOMAIN CAT-CAT1-B (DOMAIN-USER)CAT-CAT1-B
DEFINE-STANARD-DOMAIN CBASIC-500-B (DOMAIN-USER)CBASIC-500-B
EXIT

Date 89.06	.16 Norsk Data A.S PROGRAM DESCRIPTION	Page :	10 of 10
Product	Name	Reg. no.	Category
	CBASIC Compiler for ND-500/5000	211035B	STPR

### 6 NEU FAR CBA-100-B06 / CBA-500-B06

- CBA-100-B06 / CBA-500-B06
   Korrekturen:
  - Das Statement "PRINT NUM(A\$(0,2)):NUM(A\$(2,2));B\$" wurde gesperrt, da es zu Fehlern bei der Codegenerierung kommen konnte. Abhilfe: "X=NUM(A\$(0,2)),Y=NUM(A\$(2,2))ØPRINT X:Y;B\$"
  - Beim Statement SECNAME "NAME" wurden Steuerzeichen im Namen äbergeben.
- CAT-MAXDATA-B06:BRF Die Datei ist neu und wird får ND-100 und RT-Programme gebraucht.
- CAT-CAT5-B06 / CAT-CAT1-B06 Es wurden Erweiterungen får den C-Compiler und den PASCAL-Compiler aufgenommen.
- CBA-SPR-2B-B06 / CBA-SPR-LIB-B06 Die Library ist neu und wurde får SPRINT (Spooling) erstellt. Siehe Anlage.
- CBA-2BANK-B06 / CBA-LIB-B06 Korrekturen:
  - Bei der Funktion UCASE(A\$) wurde die interne Begrenzung von 128 auf 512 Byte erweitert.
  - Lag die Satznummer außerhalb der Satzdatei wurde bei der Funktion DLEN Error 100 gemeldet.
  - Bei den Magnetband-Calls wurden inkorrekte Fehlernummern ausgegeben. (Band leer, Blocklængenfehler und Filemarke gelesen).
  - Bei den DISAM-Aufrufen: bei gesperrten Sætzen wurde nach ca. fånf Minuten der Error 1 gemeldet.
  - Bei Remote-DISAM wurden die Funktionen REMOTE-KILL, REMOTE-CLOSE, REMOTE-KINV, REMOTE-COKEY und REMOTE-DALT korrigiert.
  - Bei 16 Zeichen langen USERNAMEN wurden die Filenamen nicht richtig erkannt.
  - Bei der Funktion RUN wird jetzt auch das DOMAIN-Format des neuen Linkers beräcksichtigt.

#### Neu:

- Der Call MOVE TO (siehe Anlage).